

Technical Notes On:

Alpha Anywhere 'Storage'

Contents

Overview	5
Connection Strings	5
Connection String Properties	6
Disk	6
Azure	7
Azure Test Storage	7
AmazonS3	8
How it All Works	9
Error Handling	10
Important – A5Storage Objects are State-full!	10
The A5Storage Namespace	11
A5Storage::DataContainer	11
Properties	11
DecryptConnectionString	11
DeleteItem	12
EncryptConnectionString	12
GetItem	13
ListItems	13
Open	14
ReferenceItem	15
SaveItemToFile	16
SetItem	16
SetItemFromFile	16
WriteItemToStream	17
ShowConnectionStringDialog	18
A5Storage::SubContainer	20
Properties	20
DeleteItem	20
GetItem	21
ListItems	21
Open	22
ReferenceItem	23
SaveItemToFile	24
SetItem	24
SetItemFromFile	25
WriteItemToStream	26
A5Storage::DataItem	27
Properties	27
Delete	27
Get	28

SaveToFile	28
Set	29
SetFromFile.....	29
WriteToStream.....	30
A5Storage::NameCache.....	31
Properties	31
Constructors	31
AddItems	32
Clear	32
Find	32
Set	33
Using A5Storage::NameCache with Containers.....	34
Using Storages with Uploaded Files	36
INET::UploadedFile::SaveToStorage.....	36
Basic Example	36
A Complete Example of an A5W Page	37

Overview

A5Storage is both the Alpha Anywhere root namespace and the assembly name for an object that accesses data from a container without the caller needing to explicitly know where that container is or how the data is accessed. Client code passes a connection string to the implementation; which uses the information in that string to perform the requested operations.

There are currently three implementations of A5Storage:

Disk	Uses disk functions to read and write a file based object
Azure	Uses the .NET API to access Azure Blob Storage objects
AmazonS3	Uses the Amazon AWS client .NET assembly to access S3 objects

For performance reasons, many of the functions to reference a storage object will not attempt to connect to the server until a function is called (and only if that function needs to return data from the remote server). Because connections must be reestablished for each call, errors may occur at any time. Do not assume that a successful return from an Open or Reference function means that the container exists or that a connection has been successful.

There are two objects you will interact with. The **Container** can get and set object data and may be all you need. The **Dataltem** is used when you want to create a reference to an object (without necessarily reading the data) and get information about it.

Connection Strings

To keep the user of A5Storage agnostic about the storage type, the storage container is opened using a connection string similar to a SQL database connection string. Changing the connection string changes the storage used. A connection string dialog is included in the assembly in order to make it easier to create connection strings at development time or to prompt for information when configuring a server.

Connection String Properties

Connection strings will differ depending on the implementation used. The syntax of the connection string is simply a list of property value assignments of the form:

<property name>=<value.>...

For example:

```
"Provider='Disk';Container='C:\A5WebRoot';"
```

Note: The single quotes around the value and the terminating semi-colon for each item are required.

One common property is the provider itself. The keyword for the provider is, of course, "Provider". Its value may be 'Azure', 'AmazonS3' or 'Disk'.

A second property available is Timeout. This property is the number of milliseconds a request should be limited to. Note: Azure and AmazonS3 are the only providers that currently support the timeout parameter explicitly, but it can be set for all providers.

Disk

Disk storage may be either local to the machine or available over the network (using UNC names).

In addition, you may specify a local or domain user account and password to be used to access the path you specify.

Examples

```
"Provider='Disk';Container='C:\A5WebRoot';"
```

```
"Provider='Disk';Container='\\MyServer\MyShare\A5WebRoot';Account='Bob';Password='Secret';"
```

The properties available for the Disk provider are:

- Provider
- Container
- Account (optional)
- Password (optional)
- Timeout (optional)

Azure

For Azure storage you will need to have your account and access key as well as the container name. The connection string format is:

Example

```
"Provider='Azure';Account='MyAccount';AccessKey='MyKey';Container='MyContainer';"
```

The properties available for the Azure provider are:

- Provider
- Account
- AccessKey
- Container
- Timeout (optional)

Azure Test Storage

For Azure storage, there is an additional option, the test container. If you have installed the Azure SDK and want to test with Azure test storage, you can do so either through the dialog or by setting the connection string as follows:

Example

```
"Provider='Azure';UseDevelopmentStorage='true';Container='MyContainer>';"
```

The properties available for the Azure provider when using test storage are:

- Provider
- UseDevelopmentStorage
- Container
- Timeout (optional)

AmazonS3

For Amazon S3 storage you will need to have your access key and your secret key as well as the container name. The connection string format is:

Example

```
"Provider='AmazonS3';AccessKey='MyKey';SecretKey='MySecret';Container='MyContainer';"
```

The properties available for the Azure provider are:

- Provider
- Account
- AccessKey
- Container
- Timeout (optional)

How it All Works

In order to access remote data, you first create a connection string (as discussed above). Next you create a reference to a container by calling the static container method `Open()`. The container reference can be used to access items inside of it. If you want to hold on to a reference to an item, the container provides a method to do so.

For example, the script below opens a container (a disk folder in this case) and retrieves an object and its content type:

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"  
dim Container          as A5Storage::DataContainer = null_value()  
dim Item               as A5Storage::DataItem = null_value()
```

```
CallResult = A5Storage::DataContainer::Open(Container, \  
                                                "Provider='Disk';Container='c:\A5Webroot';")  
?CallResult.Success
```

```
? Container.ReferenceItem(Item, "speak.html")  
?Container.CallResult.Success  
.T.
```

```
?Item.ModifiedTime  
= 09/29/2010 09:44:59 41 pm
```

```
?Item.ContentType  
= "text/html"
```

```
?Item.Size  
= 362
```

```
dim Text AS C  
dim ContentType as C  
Item.Get(Text, ContentType)  
?Text  
= <!DOCTYPE html PUBLIC "-//W3C//DTD XHTML 1.0 Strict//EN"  
  "http://www.w3.org/TR/xhtml1/DTD/xhtml1-strict.dtd">  
<HTML xmlns="http://www.w3.org/1999/xhtml" lang="en" xml:lang="en">  
<HEAD>  
<BODY>  
  Speaking a message.  
<EMBED src="Message.wav" autostart=true loop=false volume=100  
  hidden=true><NOEMBED><BG SOUND src="Message.wav"></NOEMBED>  
</BODY>  
</HTML>
```

```
?ContentType  
= "text/html"
```

Error Handling

Important – A5Storage Objects are State-full!

Do not share A5Storage objects across threads! Share the connection string for the container and the item name, but create a new object every time. Most functions save the error state as a member variable and return a Boolean true or false to indicate success or failure. If you share an object and two different users make overlapping calls, the status of one of the calls may be overwritten.

In order to work better with XBasic, the C# classes return either a Boolean (instance functions) or a CallResult (static functions) with detailed error information.

Again, **DO NOT SHARE INSTANCES OF A5Storage::DataContainer OR A5Storage::DataItem ACROSS THREADS!** The instance functions return a Boolean true or false and hold the result of the last error in the CallResult property. If you make a second function call, the result of the last call is lost.

The "right" way to call functions from XBasic:

Instance:

```
dim Result as CallResult
if .not. Item.Myfunction(.....) ' check for failure
    Result = Item.CallResult ' save the call result off
```

Static:

```
Result = Container.Function(...)
```

The A5Storage Namespace

A5Storage::DataContainer

This class manages access to a specific data container. This can be an Azure Blob Storage account, an Amazon S3 Storage bucket or a folder on disk. It acts as the reference point from which other objects are referenced.

Notes:

1. Object names can include paths (indicated with forward slashes '/').
2. If you are referencing an object on disk, you can include a path that will act as the root of all other objects. The object path will be the concatenation of the disk path of the container and the path embedded in the storage name (as a relative path).

Properties

Property	Type	Example Content
CallResult	P	
ConnectionString	C	" Provider='Disk';Container='C:\A5WebRoot';"
Exists	C	Returns true if the container exists.
Name	C	"C:\A5WebRoot"
StorageType	C	"Disk"

DecryptConnectionString

Use this function to decrypt a connection string if you have the passphrase (or the passphrase is defaulted).

```
STATIC DecryptConnectionString AS CallResult (  
    BYREF DecryptedString AS C,  
    ConnectionStringIn AS C  
[, PassphraseIn AS C])
```

Example

```
dim cr as CallResult  
dim ConnectionString as C  
dim ResultString as C  
cr = A5Storage::DataContainer::DecryptConnectionString( ResultString,  
                                                         ConnectionString)  
  
?cr.Success
```

DeleteItem

This function will delete an object. If the object does not exist, no error will be returned.

DeleteItem AS L (TargetPath AS C)

Example

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim Container      as A5Storage::DataContainer = null_value()
dim Item           as A5Storage::DataItem = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
"Provider='Disk';Container='c:\A5Webroot';")
?CallResult.Success
?Container.DeleteItem("MyTargetPath/MyObject")
```

EncryptConnectionString

Use this function to encrypt a connection string.

Note: If you do not provide a passphrase then it will be defaulted. Only this assembly will be able to decrypt the string, but anyone with the assembly will be able to decrypt it.

```
STATIC EncryptConnectionString AS CallResult (
    BYREF EncryptedString AS C
    ConnectionStringIn    AS C
    [, PassphraseIn       AS C])
```

Example

```
dim cr as CallResult
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim ResultString     as C
cr = A5Storage::DataContainer::EncryptConnectionString( ResultString,
    ConnectionString,
    "secret");
```

GetItem

Retrieves an item from the container using the name you provide. The content type is also returned.

Note: You must dimension the resulting Data variable and the ContentType variable prior to making the call.

```
GetItem AS L (    BYREF Data          AS B,
                  BYREF ContentType   AS C,
                  TargetPath          AS C)

GetItem AS L (    BYREF Data          AS C,
                  BYREF ContentType   AS C,
                  TargetPath          AS C)
```

Example

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim ResultData       as B
dim ContentType      as C
dim Container        as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
"Provider='Disk';Container='c:\A5Webroot';")
?CallResult.Success

?Container.GetItem(ResultData, ContentType, "MyFile.jpg")
```

ListItems

Lists the contents of the container as a CRLF() delimited string.

```
ListItems AS L (BYREF String as C [, SearchPrefix as C])
```

Example

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim ResultString     as C
dim Container        as A5Storage::DataContainer = null_value()
dim Item             as A5Storage::DataItem = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
"Provider='Disk';Container='c:\A5Webroot';")
?CallResult.Success
?Container.ListItems(ResultString)
Showvar(ResultString)
```

Open

Opens (references) a storage container based on a connection string.

Note: If the connection string is encrypted, the passphrase must be provided or the container will attempt to decrypt the connection string using the default passphrase. See the function `EncryptConnectionString` for more information.

```
STATIC Open AS CallResult (
    BYREF      NewContainer      AS A5Storage::DataContainer,
               ConnectionStringIn AS C
               [, Passphrase     AS C])
```

```
STATIC Open AS CallResult (
    BYREF      NewContainer      AS A5Storage::DataContainer,
               Cache             AS A5Storage::NameCache,
               ConnectionStringIn AS C
               [, Passphrase     AS C])
```

Examples

```
dim CallResult as CallResult
dim Container as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                             "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    ...
```

OR

```
dim CallResult as CallResult
dim Container as A5Storage::DataContainer = null_value()
dim Storages as C = <<%txt%
    Storage1      Provider='Disk';Container='C:\A5WebRoot1';
    Storage2      Provider='Disk';Container='C:\A5WebRoot2';
    %txt%
dim Cache as A5Storage::NameCache = new A5Storage::NameCache(Storages)

CallResult = A5Storage::DataContainer::Open(Container, Cache,\
                                             "::NAME::MyConnectionString")
if CallResult.Success
    ...
```

Note: The connection string passed in the second example does NOT have to be a named connection. If you DO pass a named connection, you must also provide a cache to look it up in.

Referenceltem

Creates and returns a reference to an item within the container.

Notes:

1. You must dimension Item before making the call.
2. No data is actually read until you ask for it.

```
Referenceltem AS L (BYREF Item AS A5Storage::DataItem,  
TargetPath AS C)
```

Example

```
dim CallResult as CallResult  
dim Container as A5Storage::DataContainer = null_value()  
  
CallResult = A5Storage::DataContainer::Open(Container, \  
"Provider='Disk';Container='c:\A5Webroot';")  
if CallResult.Success  
    Dim Item A5Storage::DataItem = null_value()  
    Container.Referenceltem(Item, "MyObjectName")  
    ...
```

SaveItemToFile

SaveItemToFile AS L (SourcePath AS C, TargetPath AS C)

Example

```
dim CallResult as CallResult
dim Container as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                           "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    ?Container.SaveItemToFile("MyItempath/MyItem.jpg", \
                             "c:\temp\MyItem.jpg")
...

```

SetItem

SetItem AS L (Source AS B, ContentType AS C, TargetPath AS C)

SetItem AS L (Source AS C, ContentType AS C, TargetPath AS C)

SetItem AS L (Source AS System::IO::Stream,
 ContentType AS C, TargetPath AS C)

Example

```
dim CallResult as CallResult
dim Container as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                           "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    ?Container.SetItem("<html><body>Hello World</body> </html>", \
                     "text/html", \
                     "MyPath/ MyItem.html")
...

```

SetItemFromFile

SetItemFromFile AS L (SourcePath AS C,
 ContentType AS C, TargetPath AS C
 [, Offset as N = 0 [, Length as N = -1]])

Example

```
dim CallResult as CallResult
dim Container as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                           "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    ?Container.SetItemFromFile ( "c:\temp\MyItem.jpg", \
                                "MyItempath/MyItem.jpg")
...

```


WriteItemToStream

Retrieves an item from the container using the name you provide. The content type is also returned. The item is written to the stream you provide.

Note: You must dimension the resulting Stream, Length and ContentType variables prior to making the call.

```
WriteItemToStreamStream AS L (
    Stream      AS System::IO::Stream
    BYREF Length AS N,
    BYREF ContentType AS C,
    TargetPath  AS C)
```

Example

```
dim Stream      as System::IO::Stream = null_value()
dim ContentType as C
dim Length      as N
dim Buffer      as B
dim CallResult  as CallResult
dim Container   as A5Storage::DataContainer = null_value()

Stream = new System::IO::MemoryStream()
CallResult = A5Storage::DataContainer::Open(Container, \
    "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    if Container.WriteItemToStream(Stream, Length, ContentType, "Speak.a5w")
        Stream.Seek(0, System::IO::SeekOrigin::Begin)

        dim Reader as System::IO::BinaryReader = \
            new System::IO::BinaryReader(Stream)
        Buffer = Reader.ReadBytes(Length)
        Stream.close()
    else
        CallResult = Container.CallResult
    end if
end if

if CallResult.Success
    showvar("Type: " + ContentType + crlf() + "Length: " + Length + crlf(2) + buffer, \
        "Success")
else
    showvar(CallResult.Text, "Error")
end if
```

ShowConnectionStringDialog

This function displays a connection string dialog and returns a clear text or encrypted password. The function returns a call result which indicates whether the dialog was exited by clicking OK or Cancel, or if an error occurred in decrypting/encrypting the connection string.

The EncryptResponse parameter is used to set the initial value of the Encrypt Connection String checkbox.

The Passphrase parameter is used to decrypt the connection string (if it is encrypted). If the decryption succeeds, the value is used to set the initial value of the Encryption Passphrase text box. If the decryption fails (or a passphrase is not provided), a dialog prompts the user for a passphrase until they either enter the correct one, or they click the Cancel button.

The user can check or uncheck the Encrypt Connection String checkbox or the text value of Encryption Passphrase before returning from the dialog. If the checkbox is set and OK is clicked, the connection string is encrypted using the current value of the Encryption Passphrase text box.

```
STATIC ShowConnectionStringDialog AS CallResult (  
    BYREF      ConnectionStringResult AS C  
    ConnectionStringIn AS C  
    [, EncryptResponse AS L  
    [, Passphrase AS C]])
```

Example

```
dim ConnectionString as C  
dim CR as CallResult  
CR = A5Storage::Container::ShowConnectionStringDialog( ConnectionString,  
    ConnectionString,  
    .t., "mysecret")
```

Storage Connection String Builder

Storage Provider
Azure

☐ Use Test Storage

Account
[Empty Text Box]

Access Key
[Empty Text Box]

☐ Show Access Key

Container Name
[Empty Text Box]

☐ Encrypt Connection String
Encryption Passphrase
[Empty Text Box]

Test Connection
☐ Container Must Exist

Request Timeout (milli-seconds) 10000

Show Connection String OK Cancel

A5Storage::SubContainer

This class manages access to a specific "folder" or "sub-path" within a data container. As with the DataContainer object, it acts as the reference point from which other objects are referenced below it in the hierarchy. It does that by maintaining a "prefix" or "path" if you will, which all references are assumed to include.

Notes:

1. If you are referencing an object on disk, the prefix is intended to be a folder or partial folder path. The full object path will be the concatenation of the disk path of the container, the prefix and the path embedded in the storage name (as a relative path).
2. A slash ("/") is added to each part of the container/sub-container hierarchy to form the full path to the storage object.

Properties

Property	Type	Example Content
CallResult	P	
Prefix	C	"logs" – a partial path
Container	P	Parent Container

DeleteItem

This function will delete an object. If the object does not exist, no error will be returned.

DeleteItem AS L (TargetPath AS C)

Example

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim SubContainer as A5Storage::SubContainer = null_value()
dim Item as A5Storage::DataItem = null_value()

CallResult = A5Storage::SubContainer::Open(SubContainer, \
    "Provider='Disk';Container='c:\A5Webroot';", \
    "logs")

?CallResult.Success
?SubContainer.DeleteItem("MyTargetPath/MyObject")
```

GetItem

Retrieves an item from the container using the name you provide. The content type is also returned.

Note: You must dimension the resulting Data variable and the ContentType variable prior to making the call.

```
GetItem AS L (    BYREF Data          AS B,
                  BYREF ContentType    AS C,
                  TargetPath            AS C)

GetItem AS L (    BYREF Data          AS C,
                  BYREF ContentType    AS C,
                  TargetPath            AS C)
```

Example

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim ResultData       as B
dim ContentType      as C
dim SubContainer      as A5Storage::SubContainer = null_value()

CallResult = A5Storage::SubContainer::Open(Container, \
                                             "Provider='Disk';Container='c:\A5Webroot';", \
                                             "logs")

?CallResult.Success

?SubContainer.GetItem(ResultData, ContentType, "MyFile.jpg")
```

ListItems

Lists the contents of the container as a CRLF() delimited string.

```
ListItems AS L (BYREF String as C [, SearchPrefix as C])
```

Example

```
dim ConnectionString as C = "Provider='Disk';Container='C:\A5WebRoot';"
dim ResultString      as C
dim SubContainer       as A5Storage::SubContainer = null_value()
dim Item              as A5Storage::DataItem = null_value()

CallResult = A5Storage::SubContainer::Open(Container, \
                                             "Provider='Disk';Container='c:\A5Webroot';", \
                                             "logs")

?CallResult.Success
?SubContainer.ListItems(ResultString)
Showvar(ResultString)
```

Open

Opens (references) a storage container based on a connection string and the prefix provided.

```
STATIC Open AS CallResult (
    BYREF      SubContainer      AS A5Storage::SubContainer,
               ConnectionStringIn AS C
               Prefix            AS C
               [, Passphrase     AS C])
```

```
STATIC Open AS CallResult (
    BYREF      SubContainer      AS A5Storage::SubContainer,
               Cache             AS A5Storage::NameCache,
               ConnectionStringIn AS C
               Prefix            AS C
               [, Passphrase     AS C])
```

Examples

```
dim CallResult      as CallResult
dim SubContainer    as A5Storage::SubContainer = null_value()

CallResult = A5Storage::SubContainer::Open(SubContainer, \
                                             "Provider='Disk';Container='c:\A5Webroot';", \
                                             "logs")

if CallResult.Success
    ...
```

OR

```
dim CallResult      as CallResult
dim SubContainer    as A5Storage::SubContainer = null_value()
dim Storages as C = <<%txt%
    Storage1        Provider='Disk';Container='C:\A5WebRoot1';
    Storage2        Provider='Disk';Container='C:\A5WebRoot2';
    %txt%
dim Cache as A5Storage::NameCache = new A5Storage::NameCache(Storages)
```

```
CallResult = A5Storage::SubContainer::Open(SubContainer, Cache, \
                                             "::::MyConnectionString", \
                                             "logs")

if CallResult.Success
    ...
```

Note: The connection string passed in the second example does NOT have to be a named connection. If you DO pass a named connection, you must also provide a cache to look it up in.

Referenceltem

Creates and returns a reference to an item within the container.

Notes:

1. You must dimension Item before making the call.
2. No data is actually read until you ask for it.

```
Referenceltem AS L (BYREF      Item      AS A5Storage::DataItem,  
                    TargetPath AS C)
```

Example

```
dim CallResult      as CallResult  
dim SubContainer    as A5Storage::SubContainer = null_value()  
  
CallResult = A5Storage::SubContainer::Open(SubContainer, \  
                                           "Provider='Disk';Container='c:\A5Webroot';", \  
                                           "logs")  
  
if CallResult.Success  
    Dim Item A5Storage::DataItem = null_value()  
    SubContainer.Referenceltem(Item, "MyObjectName")  
    ...
```

SaveltemToFile

SaveltemToFile AS L (SourcePath AS C, TargetPath AS C)

Example

```
dim CallResult      as CallResult
dim SubContainer    as A5Storage::SubContainer = null_value()

CallResult = A5Storage::SubContainer::Open(SubContainer, \
                                           "Provider='Disk';Container='c:\A5Webroot';", \
                                           "logs")

if CallResult.Success
    ?SubContainer.SaveltemToFile("Myltempath/Myltem.jpg", \
                                "c:\temp\Myltem.jpg")
...

```

SetItem

SetItem AS L (Source AS B, ContentType AS C, TargetPath AS C)

SetItem AS L (Source AS C, ContentType AS C, TargetPath AS C)

SetItem AS L (Source AS System::IO::Stream,
 ContentType AS C, TargetPath AS C)

Example

```
dim CallResult      as CallResult
dim SubContainer    as A5Storage::SubContainer = null_value()

CallResult = A5Storage::SubContainer::Open(SubContainer, \
                                           "Provider='Disk';Container='c:\A5Webroot';", \
                                           "logs")

if CallResult.Success
    ?SubContainer.SetItem("<html><body>Hello World</body> </html>", \
                        "text/html", \
                        "MyPath/ Myltem.html")
...

```


SetItemFromFile

```
SetItemFromFile AS L (   SourcePath AS C,  
                        ContentType AS C,  
                        TargetPath AS C  
                        [, Offset as N = 0  
                        [, Length as N = -1]])
```

Example

```
dim CallResult          as CallResult  
dim SubContainer        as A5Storage::SubContainer = null_value()  
  
CallResult = A5Storage::SubContainer::Open(SubContainer, \  
                                           "Provider='Disk';Container='c:\A5Webroot';", \  
                                           "logs")  
  
if CallResult.Success  
    ?SubContainer.SetItemFromFile ("c:\temp\MyItem.jpg", \  
                                   "MyItempath\MyItem.jpg")  
    ...  
end if
```

WriteItemToStream

Retrieves an item from the container using the name you provide. The content type is also returned. The item is written to the stream you provide.

Note: You must dimension the resulting Stream, Length and ContentType variables prior to making the call.

```
WriteItemToStreamStream AS L (
    Stream      AS System::IO::Stream
    BYREF Length AS N,
    BYREF ContentType AS C,
    TargetPath  AS C)
```

Example

```
dim Stream      as System::IO::Stream = null_value()
dim ContentType as C
dim Length      as N
dim Buffer      as B
dim CallResult  as CallResult
dim SubContainer as A5Storage::SubContainer = null_value()

Stream = new System::IO::MemoryStream()
CallResult = A5Storage::SubContainer::Open(SubContainer, \
    "Provider='Disk';Container='c:\A5Webroot';",
    "logs")

if CallResult.Success
    if SubContainer.WriteItemToStream(Stream, \
        Length, ContentType, "Speak.a5w")
        Stream.Seek(0, System::IO::SeekOrigin::Begin)

        dim Reader as System::IO::BinaryReader = \
            new System::IO::BinaryReader(Stream)
        Buffer = Reader.ReadBytes(Length)
        Stream.close()
    else
        CallResult = SubContainer.CallResult
    end if
end if

if CallResult.Success
    showvar("Type: " + ContentType + crlf() + "Length: " + Length + crlf(2) + buffer, \
        "Success")
else
    showvar(CallResult.Text, "Error")
end if
```

A5Storage::DataItem

The A5Storage::DataItem class is essentially a reference to an object within the parent container. It does not hold any data, but has methods and properties that can be used to access the object itself and to get information about it without reading the object.

Properties

Property	Type	Writeable	Example Content
AbsolutePath	C	N	URL to reference the item directly in a browser: For example: file:///c:/temp/teststorage/Hello https://a5teststorage.blob.core.windows.net/text/Hello https://s3.amazonaws.com/A5Test/Hello Note: The drive path must be a UNC path or a common drive letter assigned to a share to use the value on a LAN.
CallResult	P	N	
ContentType	C	Yes	"text/html"
ModifiedTime	T	No	09/29/2010 09:44:59 41 pm
Name	C	No	"speech/speak.html "
Size	N	No	362

Delete

Delete the underlying object if it exists. Returns false if an error occurs.

Note: No error is returned if the object does not exist.

Delete AS L ()

Example

```
dim CallResult      as CallResult
dim Container       as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                                "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    Dim Item A5Storage::DataItem = null_value()
    If Container.ReferenceItem(Item, "MyObjectName")
        if .not. Item.Delete
            showvar(Item.CallResult.Text, "Error deleting Item")
        ...
    
```

Get

Get the data for the object. The data returned may be a blob or a string, depending on the type of the Data argument you pass.

Note: You must dimension both the Data and ContentTypeResult variables before calling this function.

```
Get AS L (BYREF Data AS B, BYREF ContentTypeResult AS C)
Get AS L (BYREF Data AS C, BYREF ContentTypeResult AS C)
```

Example

```
dim CallResult      as CallResult
dim Container       as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                                "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    Dim Item A5Storage::DataItem = null_value()
    If Container.ReferenceItem(Item, "MyObjectName")

        Dim Data as B
        Dim ContentTypeResult as C
        if .not. Item.Get(Data, ContentTypeResult)
            showvar(Item.CallResult.Text, "Error in Get")
        ...
    
```

SaveToFile

Saves the data in an object to the file specified in TargetPath.

```
SaveToFile AS L (TargetPath AS C)
```

Example

```
dim CallResult      as CallResult
dim Container       as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                                "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    Dim Item A5Storage::DataItem = null_value()
    If Container.ReferenceItem(Item, "MyObjectName")
        if .not. Item.SaveToFile("c:\mydata.jpg")
    
```

Set

Sets the object value and content type based on the values passed to the function.

Note: This function also accepts a stream. There may be some cases where a stream references the data from some other object or is the result of some other .NET function call. You can pass the stream as the data argument.

```
Set AS L (Source AS B, ContentTypeIn AS C)
Set AS L (Source AS C, ContentTypeIn AS C)
Set AS L (Source AS System::IO::Stream, ContentTypeIn AS C)
```

Example

```
dim CallResult      as CallResult
dim Container       as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                                "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    Dim Item A5Storage::DataItem = null_value()
    If Container.ReferenceItem(Item, "MyObjectName")

        Dim Data                as B = File.To_Blob("Myfile.jpg")
        Dim ContentTypeResult    as C = "image/jpg"
        if .not. Item.Set(Data, ContentType)
            showvar(Item.CallResult.Text, "Error in Set")
        ...
```

SetFromFile

Set the object value from the file specified in SourcePath and sets the content based on ContentTypeIn.

```
SetFromFile AS L ( SourcePath AS C, ContentTypeIn AS C
                  [, Offset as N = 0 [, Length as N = -1]])
```

Example

```
dim CallResult      as CallResult
dim Container       as A5Storage::DataContainer = null_value()

CallResult = A5Storage::DataContainer::Open(Container, \
                                                "Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    Dim Item A5Storage::DataItem = null_value()
    If Container.ReferenceItem(Item, "MyObjectName")
        if .not. Item.SetFromFile(File.To_Blob("MyFile.jpg", "image/jpg")
            showvar(Item.CallResult.Text, "Error in SetFromFile")
        ...
```

WriteToStream

Retrieves the item data and writes it to a System::IO::Stream object. The content type and length written are also returned.

Note: You must dimension the resulting Stream and ContentType and Length variables prior to making the call.

```
WriteToStream AS L (
    Stream AS System::IO::Stream,
    BYREF LengthWritten AS N,
    BYREF ContentType AS C)
```

Example

```
dim Stream as System::IO::Stream = null_value()
dim ContentType as C
dim Length as N
dim Buffer as B
dim CallResult as CallResult
dim Container as A5Storage::DataContainer = null_value()
dim Item as A5Storage::DataItem = null_value()

Stream = new System::IO::MemoryStream()
CallResult = A5Storage::DataContainer::Open(Container,
"Provider='Disk';Container='c:\A5Webroot';")
if CallResult.Success
    if Container.Referenceltem(Item, "Speak.a5w")
        if Item.WriteToStream(Stream, Length, ContentType)
            Stream.Seek(0, System::IO::SeekOrigin::Begin)
            dim Reader as System::IO::BinaryReader = new \
                System::IO::BinaryReader(Stream)
            Buffer = Reader.ReadBytes(Length)
            Stream.close()
        else
            CallResult = Item.CallResult
        end if
    else
        CallResult = Container.CallResult
    end if
end if

if CallResult.Success
    showvar("Type: " + ContentType + crlf() + "Length: " + Length + crlf(2) + buffer,
"Success")
else
    showvar(CallResult.Text, "Error")
end if
```

A5Storage::NameCache

The A5Storage::NameCache is a container for named connection strings. The caller is responsible for managing the contents and for providing the cache to use when calling A5Storage::DataContainer::Open().

Properties

Property	Type	Writeable	Description
CallResult	CallResult	N	Contains the status of the last call made on the instance.
Names	C	Yes	Gets or sets the entire cache from or to a string of the format: "name<tab>connectionstring<crLf> ... " Each row contains a tab separated name and connection string pair. The rows are delimited with a carriage return and line feed (crLf).
NamedConnectionPrefix	C	N	:::NAME:::

Constructors

A5Storage::NameCache()

A5Storage::NameCache(Storages as C)

Example 1

```
dim Storages as C = <<%txt%
    Storage1      Provider='Disk';Container='C:\A5WebRoot1';
    Storage2      Provider='Disk';Container='C:\A5WebRoot2';
%txt%

dim Cache as A5Storage::NameCache
if Cache.AddItem(Storages)
    ...
else
    ShowVar("Oops!" + crLf() + Cache.CallResult.Text)
end if
```

Example 2

```
dim Storages as C = <<%txt%
    Storage1      Provider='Disk';Container='C:\A5WebRoot1';
    Storage2      Provider='Disk';Container='C:\A5WebRoot2';
%txt%

dim Cache as A5Storage::NameCache = new A5Storage::NameCache(Storages)
```

AddItems

AddItem AS L (NamesandValues AS C)

Example

```
Dim Cache as A5Storage::NameCache
dim Storages as C = <<%txt%
    Storage1      Provider='Disk';Container='C:\A5WebRoot1';
    Storage2      Provider='Disk';Container='C:\A5WebRoot2';
    Invalid       Provider='Disk';Container='AA:\abc';
%txt%
if Cache.AddItem(Storages)
    ...
else
    ShowVar("Oops!" + crlf() + Cache.CallResult.Text)
end if
```

Clear

Clear AS L ()

Example

```
Dim Cache as A5Storage::NameCache
Cache.Clear()
```

Find

Find AS L (Key as C, BYREF Value as C)

Example

```
dim Cache                    as A5Storage::NameCache
dim ConnectionString    as C
if Cache.Find("MyName", ConnectionString)
    ...
else
    ShowVar("Oops!" + crlf() + Cache.CallResult.Text)
end if
```


Set

Adds or replaces a connection string in the cache.

```
Set AS L (   Name           AS C,  
           ConnectionString AS C)
```

Example

```
Dim Cache as A5Storage::NameCache  
Cache.Set("MyName", "MyConnectionString")
```

Using A5Storage::NameCache with Containers

The example script below shows how you can create and use a cache of names with A5Storage::Container to automatically translate named connections.

```
dim Storages as C = <<%txt%
Storage1      Provider='Disk';Container='C:\A5WebRoot1';
Storage2      Provider='Disk';Container='C:\A5WebRoot2';
Invalid       Provider='Disk';Container='AA:\abc';
%txt%

dim TestStorages as C = <<%txt%
Storage1
Storage2
Invalid
NotFound
%txt%

Result = RunTest(Storages, TestStorages)
showvar(Result)

FUNCTION RunTest as C (Storages as C, TestStorages as C)
dim Result as C
dim cache as a5storage::namecache = new a5storage::namecache(Storages)

for i = 1 to w_count(TestStorages, crlf())
    CurrentItem = word(TestStorages, i, crlf())
    CurrentName = word(CurrentItem, 1, chr(9))
    Result = Result + "Testing Name: " + CurrentName + crlf() + TestName(Cache, "::name::" +
CurrentName)
next

RunTest = Result
END FUNCTION

FUNCTION TestName(Cache as A5Storage::NameCache, Name as C)

dim Result as C

dim sc as a5storage::datacontainer = null_value()

CallResult = A5Storage::DataContainer::Open(sc, Cache, Name)
if CallResult.Success
    dim ItemName          as C = "test/Data.Txt"
    dim ItemValue         as C = "StorageData"
    dim ItemContentType as C = "text"

    if sc.SetItem(ItemValue, ItemContentType, ItemName)

        dim di as A5Storage::DataItem = null_value()

        if sc.ReferenceItem(di, ItemName)
            dim Text AS C
            dim ContentType as C
```

```

        di.Get(Text, ContentType)
        Result = "Item: " + ItemName + " = " + Text + crlf()
        Result = Result + chr(9) + chr(9) + "Modified: " + di.ModifiedTime + crlf()
        Result = Result + chr(9) + chr(9) + "ContentType: " + di.ContentType + crlf()
        Result = Result + chr(9) + chr(9) + "Size: " + di.Size + crlf(2)
    else
        Result = "Error referencing item '" + ItemName + "': " + sc.CallResult.Text
    end if
else
    Result = "Error setting item: " + sc.CallResult.Text + crlf()
end if
else
    Result = "Error opening container '" + Name + "': " + CallResult.Text + crlf()
end if
TestName = Result
END FUNCTION

```

Using Storages with Uploaded Files

The class `INET::UploadedFile` now has a method to allow saving an uploaded file directly to a storage. This method bypasses memory altogether and saves the file from disk to the storage using buffered reads and writes.

INET::UploadedFile::SaveToStorage

```
INET::UploadedFile::SaveToStorage as L ( DestinationStorage  as P,  
                                         TargetMember      as C,  
                                         ContentType        as C)
```

Note: `DestinationStorage` can be either an instance of `A5Storage::DataContainer` or an instance of `A5Storage::SubContainer`.

Basic Example

```
if eval_valid("Request.Variables.File1")  
  
    DiskContainerName    = "C:\Temp\Disk"  
    DiskConnectionString = "Provider='Disk';Container=" + DiskContainerName + ";"  
  
    File                = Request.Variables.File1  
    FileName            = File.FileName  
    FileSize            = File.Size  
    FileContentType     = File.ContentType  
  
    ? "File uploaded: " + FileName + " (" + FileSize + " bytes)<br/>"  
  
    dim Storage as A5Storage::SubContainer = null_value()  
  
    CallResult = A5Storage::SubContainer::Open(Storage, DiskConnectionString, "Test1")  
    if CallResult.Success  
        if File.SaveToStorage(Storage, FileName, FileContentType)  
            ? "File written to storage: " + FileName + " (" + FileSize + " bytes in " + \  
        else  
            ? "File write to storage failed: " + File.CallResult.Text + "<br/>"  
        end if  
    else  
        ? "File upload failed.  Unable to open storage." + CallResult.Text + "<br/>"  
    end if  
end if
```

A Complete Example of an A5W Page

```
<html>
<head><title>File Upload</title></head>
<body>
<%a5
if eval_valid("Request.Variables.File1")

    DiskContainerName          = "C:\Temp\Disk"
    DiskConnectionString       = "Provider='Disk';Container=" + DiskContainerName + ";"

    AzureAccountName           = "a5webservertest"
    AzureAccessKey              = "<your access key here"
    AzureContainerName          = "a5webservertest"
    AzureConnectionString      = "Provider='Azure';Account=" + AzureAccountName + \
        ";AccessKey=" + AzureAccessKey + ";Container=" + AzureContainerName + ";"

    AzureTestContainerName      = "a5webservertest"
    AzureTestConnectionString   = \
        "Provider='Azure';UseDevelopmentStorage='true';Container=" + \
        AzureContainerName + ";"

    AmazonAccessKey            = "<your access key>"
    AmazonSecretKey             = "<your amazon secret key>"
    AmazonContainerName         = "A5WebServerTest-Application"
    AmazonConnectionString     = "Provider='AmazonS3';AccessKey=" + \
        AmazonAccessKey + ";SecretKey=" + \
        AmazonSecretKey + ";Container=" + AmazonContainerName + ";"

    dim ConnectionStrings[4] as C = [ DiskConnectionString, AzureConnectionString, \
        AzureTestConnectionString, AmazonConnectionString ]

    dim Timer as Util::Timer
    File                        = Request.Variables.File1
    FileName                   = File.FileName
    FileSize                   = File.Size
    FileContentType            = File.ContentType

    ? "File uploaded: " + FileName + " (" + FileSize + " bytes)<br/><br/>"

    dim Storage as A5Storage::SubContainer = null_value()
    for i = 1 to ConnectionStrings.Size()
        ConnectionString = ConnectionStrings[i]
        ? "Opening connection string at index " + i + " - " + ConnectionString + ". " + "<br/>"

        Storage = null_value()

        CallResult = A5Storage::SubContainer::Open(Storage, ConnectionString, "Test1")
        if CallResult.Success
            dim UploadTimer as Util::Timer
            UploadTimer.Start()

            if File.SaveToStorage(Storage, FileName, FileContentType)
                ? "File written to storage: " + FileName + " (" + FileSize + " bytes in " + \
                    UploadTimer.ElapsedMilliseconds + " milliseconds.)<br/>"
            else
                ? "File write to storage failed: " + File.CallResult.Text + "<br/>"
            end if
        else
    end if
```

```

        ? "File upload failed. Unable to open storage." + CallResult.Text + "<br/>"
    end if
    ? "<br/>"
next
Response.Write("<hr/>")
? "Total time to save: " + Timer.ElapsedMilliseconds + " milliseconds." + "<br/>"
Response.Write("<hr/>")

end if
%>

<form action="<%a5 ?Request.ScriptName%>" method="post" enctype="multipart/form-data">
<input type="file" name="File1"/><br/>
<input type="submit" name="cmd" value="Upload File"/>
</form>

</body>
</html>

```